


# Boxford Ltd


## Boxford machine USB Driver installation instructions

1. **IMPORTANT** - DO NOT CONNECT THE MACHINE until the USB driver has been installed.
2. Insert the Boxford CAD/CAM Design Tools USB driver disk into the CD/DVD ROM drive.
3. The driver installation should boot up automatically, if not:
  - Select Start > Run
  - Type d:\BoxfordUSBDriver and press ENTER.
4. After a pause, the driver installer launches and displays the window shown below.




Select a destination folder for the driver install followed by **INSTALL**

5. The window below is shown.



The scan may take a few minutes to complete depending on your system.

6. When the driver installation is complete, the window below is shown.



Select **OK**.

7. Connect one end of the USB cable to the machine and the other end to a free USB slot on the PC.

**NOTE:** The machine must be connected to the PC before the 'CAD/CAM Design Tools' application is run. The USB connection will self configure.